SAMSUNG

< Unified Settings.csv> Data Detail

File Name

Unified Settings.csv

File Description

This file has information about your settings list for Backup and Restore. This item was supported up to P OS and later it will become end of service.

List all field names and description that is in the above file.

Field Name	Sub Field Name	Description
Key	BACKUP_Settings	Data key
TIMESTAMP	1572600000000	Time when the data was created on the terminal
CREATETIME	1572600000000	Time created in server Database
SIZE	63832	Data size
VALUE	/SoftwareUpdate/WifiAutoDownload	Download software updates automatically when connected to a Wi-Fi network
	/AOD/ContentToShow	Content to show type
	/AOD/Brightness	Auto brightness on/off
	/AOD/Time	AOD schedule
	/AOD/StateMode	AOD state (true:on / flase:off)
	/AOD/ClockType	The feature to check if AOD clock types are old Selected AOD clock type Selected LockScreen clock type Selected AOD clock type in Dream model Image Clock name Image Clock bitmap resource Image Clock type
	/AOD/WorldClockInfo	The information of stored cities for world clock The time zone information of stored cities for world clock The unique ID of stored cities for world clock
	/AOD/TapToShow	AOD tap to show setting value (0: off / 1 : on)
	/AOD/ShowMusicInformation	Decide if showing musin information on AOD (0 : gone / 1 : visible)
	/AOD/ScreenOrientation	Screen orientation value of AOD (0: portrait / 1 : landscpae)
	/AOD/ClockColor	Selected color description of AOD Clock in clock style Settings

		Selected color description of LOCK Clock in clock style Settings Selected custom color value of LOCK Clock in color picker of clock style Settings
	/AOD/ChargingInfoAlways	Determines whether to show Charging Info when AOD is turned off. (-1 : Not support charging info always, 0 : charging info alwayso off, 1 : charging info always on)
	/Settings/Advanced/DirectCall	Direct call on/off
	/Settings/Advanced/EasyMute	Easy mute on/off Motion turn over Palm touch
	/Settings/Advanced/PalmSwipeToCapture	Palm swipe to capture on/off
	/Settings/Advanced/SmartAlert	Smart alert on/off
	/Settings/Advanced/SmartCapture	Smart capture on/off
	/Settings/Advanced/SmartStay	Smart stay on/off
	/Settings/Advanced/SwipeToCallOrSendMessage	Swipe to call or send message on/off
	/Settings/Advanced/DirectShare	On / off value of Direct share setting
	/Settings/Advanced/ReduceAnimations	On / off value of Reduce anmations settings
	/Settings/Advanced/LiftToWake	On / off value of Lift to wake setting
	/Settings/Advanced/DoubleTapToWake	On / off value of Double tap to wake setting
	/Settings/Advanced/OneHandedMode	On / off value of one handed mode setting Gesture / Button mode value of one handed mode setting
	/Settings/Advanced/FingerSensorGestures	On / off value of finger sensor gesture setting
	/Settings/Advanced/CoverTextDirection	Text direction value of Clear view cover Setting
	/Settings/Advanced/ActiveKeyShortPress	Short press item value of Xcover key setting
	/Settings/Advanced/ActiveKeyLongPress	Long press item value of Xcover key setting
	/Settings/Advanced/ActiveKeyOnLockScreen	On / off value of while on Lock screen in Xcover key setting
	/Settings/Advanced/XcoverKeyPtt	If the Verizon PTT menu is On as a VZW business operator only menu of the Xcover model, let the Xcover key be used as a PTT only key. When changing to Off, the user can set it to the desired function such as the existing XCover model.
	/Settings/Advanced/SideKeyDoublePressSwitch	On / off value of Double press in Side key Setting

	/Settings/Advanced/SideKeyDoublePressType	Double press type value in Side key Setting
	/Settings/Advanced/SideKeyDoublePressOpenAppValue	Double press item value in Side key Setting
	/Settings/Advanced/SideKeyLongPressType	Long press type value in Side key Setting
	/Settings/Advanced/XcoverTopKeyShortPress	App Component used for Top key press of Xcover Pro model
	/Settings/Advanced/XcoverTopKeyLongPress	App Component used for Top key press and hold of Xcover Pro model
	/Settings/Advanced/XcoverTopKeyOnLockScreen	Switch whether to use the top key of the Xcover Pro model at lock screen.
	/Settings/Advanced/ShakeToShare	Function enabled (0: OFF / 1: ON)
	/Settings/Advanced/SmartPopupView	Package name list(: is separator)
	/Settings/Connections/Location	Location on/off
	/Settings/Connections/LocationMethod	Location method type
	/Settings/Connections/LocationBluetoothScan	Bluetooth scanning on/off
	/Settings/Connections/LocationWifiScan	Wi-Fi scanning on/off
	/Settings/Connections/Nfc/	NFC mode Android beam on/off Android Beam State
	/Settings/Connections/WiFi/Advanced/SwitchToMobileData/Aggressive	Switch to mobile data mode
	/Settings/Connections/WiFi/Advanced/SwitchToMobileData/Enabled	Switch to mobile data on/off
	/Settings/Connections/WiFi/Advanced/SwitchToMobileData/IndividualApps	Switch for individual apps on/off
	/Settings/Connections/WiFi/Advanced/AutoWifi	Turn on Wi-Fo automatically on/off
	/Settings/Connections/WiFi/Advanced/WifiPowerSavingMode	Wi-Fo power saing mode on/off
	/Settings/Connections/WiFi/Advanced/Hotspot20/Enabled	Hotspot 2.0 on/off
	/Settings/Connections/WiFi/Advanced/Hotspot20/History	Connection hostory of Hotspot 2.0 access point
	/Settings/Connections/WiFi/Advanced/ShowNetworkInfo/Enabled	Function enabled (0: OFF / 1: ON)
	/Settings/Connections/WiFi/Advanced/WIPS	WIPS on/off
	/Settings/Display/AutoBrightness	Auto brightness on/off
	/Settings/Display/BlockAccidentalTouches	Block accidential touches on/off
	/Settings/Display/BluelightFilter	Blue light filter on/off Blue light filter opacity Blue light filter schedule on/off Blue light filter schedule start time Blue light filter schedule end time Blue light filter schedule type
	/Settings/Display/FontSize	Font size index Font size range
	/Settings/Display/FontStyle	Font style Font file name

	/Settings/Display/ScreenTimeout	Screen timeout
	/Settings/Display/ScreenZoom	Screen zoomout index Screen zoom Index range
	/Settings/Display/ButtonLayout	Button order of navigation bar
	/Settings/Display/UnlockWithHomeButton	Unlock with Home button on/off
	/Settings/Display/ShowBatteryPercentage	Show battery percentage on/off
	/Settings/Display/ShowRecentNotificationOnly	Show recent notification on/off
	/Settings/Display/NightMode	Turn on now setting on/off Turn on as scheduled setting on/off Detail setting for Turn on as scheduled setting Start time for custom setting End time for custom setting Applied Dark mode Wallpaper (1: on, 0: off)
	/Settings/Display/ScreenMode	Screen mode type Automatic mode setting on/off User setting value for White balance User setting value for Advanced setting (Red) of White balance User setting value for Advanced setting (Green) of White balance User setting value for Advanced setting (Blue) of White balance
	/Settings/Display/ScreenResolution	Current resolution index value
	/Settings/Display/NavigationBar/NavigationTypes	Navigation bar mode Navigation bar detailed gestrual mode Set the sensitivity of back gestures (Only supports side and bottom gesture)
	/Settings/Display/NavigationBar/NavigationGestureHint	Show gesture hint
	/Settings/Display/HardPressHomeButton	Set home button pressure level
	/Settings/Display/ShowButtonToHideKeyboard	Show back icon when user set navigation bar as gestural mode
	/Settings/Display/ScreenSaver	Screen saver setting on/off
	/Settings/Display/TouchSensetivity	Touch sensetivity setting on/off
	/Settings/Display/FontBold	Bold font Settings on / off
	/Settings/Display/ShowChargingInformation	Charging information display value on : 1, off : 0, unsupport : -1
	/Settings/General/ShowKeyboardButton	Show keyobard button on/off
	/Settings/General/ChangeLanguageShortcut	Shift + Space : 1 Control + Space : 2 Shift + Space, Control + Space : 3 Left Alt + Shift : 4 Shift + Space, Left Alt + Shift : 5 Control + Space, Left Alt + Shift : 6 Shift + Space, Control + Space, Left Alt + Shift : 7

	/Settings/LockScreen/RoamingClock	Roaming clock on/off
	/Settings/LockScreen/RoamingClockHomeCity	Home City timezone of Roaming Clock
	/Settings/LockScreen/RoamingClockPosition	Roaming clock position
	/Settings/LockScreen/FaceWidget	Face widget order and on/off
	/Settings/LockScreen/FaceWidgetPosition	facewidget position
	/Settings/LockScreen/HideContent	Hide content on/off
	/Settings/LockScreen/NotificationIconOnly	Notification icon only on/off
	/Settings/LockScreen/ShowNotification	Lockscreen notification on/off
	/Settings/LockScreen/Transparency	Transparency of Lcokscreen notification
	/Settings/LockScreen/AutoReverseTextColor	Auto reverse text color on/off
	/Settings/LockScreen/Shortcut	Left and Right shortcut value of App shortcuts
	/Settings/LockScreen/ContactInformation	Contact Information value which shown in Lock screen
	/Settings/LockScreen/ShortcutLayout	Layout value of App shortcuts
	/Settings/LockScreen/NotificationsToShow	Show silent notifications on Lockscreen
	/Settings/LockScreen/ShowOnAOD	Show notification on AOD
	/Settings/Notifications/AppIconBadge	App icon badges on/off
	/Settings/Notifications/AppIconBadgeShowNotifications	Show notifications on Home screen on/off
	/Settings/Notifications/AppIconBadgeStyle	Badge style
	/Settings/Notifications/ShowSnoozeOption	Show snooze option icon
	/Settings/Security/MakePasswordVisible	Make password visible on/off
	/Settings/Sound/ChargingSound	Charging sound on/off
	/Settings/Sound/DialingKeypadTone	Dialing keypad tones on/off
	/Settings/Sound/KeyboardSound	Keyboard sound on/off
	/Settings/Sound/KeyboardVibration	Keyboard vibration on/off
	/Settings/Sound/NotificationSound	The name of notification sound
	/Settings/Sound/ScreenLockSound	Screen lock sound on/off
	/Settings/Sound/TouchSound	Touch sound on/off
	/Settings/Sound/UseVolumeKeyForMedia	Use Volume keys for media on/off
	/Settings/Sound/VibrationFeedback	Vibration feedback on/off
	/Settings/Sound/VibrationPattern	The name of Vibration pattern
	/Settings/Sound/VibrationWhileRinging	Vibration while ringing on/off
	/Settings/Accessibility/PreferredEngine	Preferred TTS Engine
	/Settings/Accessibility/Pitch	Pitch of text to speech
	/Settings/Accessibility/Rate	Speech rate
	/Settings/Display/BlockGesturesWithSPen	Block gestures with S Pen on/off
	/Settings/Display/BackGestureOnKeyboard	Select gestural mode, change the back gesture sensitivity value (Only supports side and bottom gesture)
	/Settings/Notifications/DndDuration	Duration contains 3 type of value - 1,0,(15-720)
	/Settings/Display/RefreshRate	Refresh rate type (0: Normal / 1: Dynamic / 2: High)
	/Settings/Sound/DialingKeypadVibration	Function enabled (0: OFF / 1: ON)

	/Settings/Sound/NavigationGesturesVibration	Function enabled (0: OFF / 1: ON)
	/Settings/Sound/CameraFeedbackVibration	Function enabled (0: OFF / 1: ON)
	/Accessibility/Mdnie/ColorAdjustmentType	Color adjustment type value(-1~4)
	/Accessibility/Mdnie/ColorLensType	Color Lens color value(0~11)
	/Accessibility/Mdnie/ColorBlindCvdseverity	Color adjustment seekbar value(0.0~1.0)
	/Accessibility/Mdnie/HighContrast	Negative color on/off value (0 or 1)
	/Accessibility/Mdnie/ColorBlind	Color blind type value (0 or 1)
	/Accessibility/Mdnie/ColorLensOpacity	Color lens opacity seekbar value(0~8)
	/Accessibility/Mdnie/ColorBlindCvdtype	Color adjustment personalize color type(0~4)
	/Accessibility/Mdnie/ColorBlindUserParameter	Color adjustment seekbar value(0.0~1.0)
	/Accessibility/Mdnie/ColorLensSwitch	Color Lens on/off value (0 or 1)
	/Accessibility/Mdnie/GreyscaleMode	GrayScale mode enable value (0 or 1)
	/Accessibility/Mdnie/PredefinedColorBlindIntensity	Color adhustment type intensity seekbar value
	/Accessibility/Default/AccessibilityAutoclickDelay	autoclick delay value(Min:200, Max: 1000)
	/Accessibility/Default/AccessibilityDisplayInversionEnabled	display inversion enable (1: on, 0:off)
	/Accessibility/Default/FlashNotification	on/off value of Camera flash notification (0:off 1:on)
	/Accessibility/Default/AccessibilityCaptioningBackgroundColor	Background color value of Google captions (0x00000000 ~ 0xFFFFFFFF)
	/Accessibility/Default/HoverZoomMagnifierSize	magnifier window size (0:small, 1:medium, 2, large)
	/Accessibility/Default/AccessControlEnabled	Current operation status of Interaction control (0:off 1:on)
	/Accessibility/Default/AccessibilityEnabled	whether the AccessibilityService is enabled or not(0 or 1)
	/Accessibility/Default/EnabledAccessibilityService	list of enabled AccessibilityService's component name
	/Accessibility/Default/DirectAccessMagnifier	on/off value of Direct access - Magnifier window (0 or 1)
	/Accessibility/Default/AccesscontrolTimeSetMin	Min value for Timer to auto stop about Interaction control (0~59)
	/Accessibility/Default/AccessControlTimeSetHour	Hour value for Timer to auto stop about Interaction control (0~23)
	/Accessibility/Default/AccessibilityLargePointerIcon	voice assistant largeMouse on/off (1: on, 0: off)
	/Accessibility/Default/NotificationReminderSelectable	whether the Notification reminder is enabled or not(0 or 1)
	/Accessibility/Default/AccessibilityCaptioningEdgeColor	Edge color value of Google captions (0x00000000 ~ 0xFFFFFFFF)
	/Accessibility/Default/AccessibilityCaptioningEdgeType	Edge type value of Google captions (-1~4)
	/Accessibility/Default/AssistantMenu	assistant menu enable (1: on, 0: off)

	/Accessibility/Default/EasyInteraction	Setting status of Single tap mode (0:off 1:on)
	/Accessibility/Default/AccessibilityShortcutEnabled	whether the Accessibility shortcut is enabled or not(0 or 1)
	/Accessibility/Default/DirectGreyscale	value to indicate Grey scale item is selected or not
	/Accessibility/Default/NotificationReminderVibrate	Setting status of Vibrate option in Notification reminder (0:off 1:on)
	/Accessibility/Default/AccessibilityLargeCursor	accessibility large cursor value
	/Accessibility/Default/MagnifierWindowHorizontalFocusLock	Horizontal focus lock on/off value (1: on, 0: off)
	/Accessibility/Default/AccessControlPowerButton	Power button blocking when Interaction contol enabled (0:on 1:off)
	/Accessibility/Default/AccessControlKeyboardBlock	SIP blocking when Interaction contol enabled (0:on 1:off)
	/Accessibility/Default/ShowButtonBackground	show buttons with outlines on/off value (1: on, 0: off)
	/Accessibility/Default/AccessControlUse	Setting status of Interaction control (0:off 1:on)
	/Accessibility/Default/AccessibilityCaptioningWindowColor	Window color value of Google captions (0x00000000 ~ 0xFFFFFFFF)
	/Accessibility/Default/AccessibilityCaptioningEnabled	on/off value of Google captions (0:off 1:on)
	/Accessibility/Default/AirMotionWakeUp	easy screen turn on state (1: on, 0:off)
	/Accessibility/Default/AccessibilityButtonTargetComponent	accessibility button target component ID
	/Accessibility/Default/AllSoundOff	on/off value of Muite all sounds (0:off 1:on)
	/Accessibility/Default/NotificationReminderAppList	list of package name which the notification reminder is enabled (seperator: ";")
	/Accessibility/Default/AccessibilityAutoclickEnabled	autoclick enable (1; on, 0: off)
	/Accessibility/Default/AccessibilityCaptioningPreset	PresetStyle type value of Google captions (-1~4)
	/Accessibility/Default/SoundDetector	on/off value of Baby crying detector (0:off 1:on)
	/Accessibility/Default/HoverZoomValue	MagnifierWindow zoom percentage (Min:0, Max:70)
	/Accessibility/Default/RapidKeyInput	Rapid key input enable value (0:off, 1: On)
	/Accessibility/Default/DirectSTalkback	value to indicate Voice assistant item is selected or not
	/Accessibility/Default/DirectAccess	on/off value of Direct Access (0:off 1:on)
	/Accessibility/Default/AccessControlVolumeButton	Volume button blocking when Interaction contol enabled (0:on 1:off)
	/Accessibility/Default/HearingAid	on/off value of Hearing aids (0:off 1:on)
	/Accessibility/Default/DirectColorAdjustment	value to indicate Color adjustment item is selected or not

	/Accessibility/Default/AccessibilityCaptioningTypeface	typeface value of Google captions
	/Accessibility/Default/FingerMagnifier	finger magnifier on/off value(1: on, 0: off)
	/Accessibility/Default/HighTextContrastEnabled	high contrast font enable value (1: on, 0: off)
	/Accessibility/Default/ScreenNotification	on/off value of Screen notification (0:off 1:on)
	/Accessibility/Default/AccessibilityShorcutOnLockScreen	shortcut on lockscreen on/off value (1: on, 0: off)
	/Accessibility/Default/AccessibilityDisplayMagnificationNavbarEnabled	magnification navibar display enable (1:on, 0:off)
	/Accessibility/Default/AccessibilityDisplayMagnificationEnabled	magnification display enable (1: on, 0:off)
	/Accessibility/Default/TimeKey	Reminder interval value of Notification reminder (60, 180, 300, 600, 900)
	/Accessibility/Default/AccessibilityCaptioningLocale	Locale value of Google captions
	/Accessibility/Default/AccessibilityCaptioningForegroundColor	Text color value of Google captions (0x00000000 ~ 0xFFFFFFFF)
	/Accessibility/Default/DirectNegative	value to indicate Negative color item is selected or not
	/Accessibility/Default/AccessibilityCursorColor	cursor color value
	/Accessibility/Default/AccessibilityCaptioningFontScale	Text size value of Google captions (0.5~2.0)
	/Accessibility/Default/DirectAccessControl	value to indicate Interaction control item is selected or not
	/Accessibility/Default/DirectTalkback	value to indicate talkback item is selected or not
	/Accessibility/Default/DirectUniversalSwitch	value to indicate Universal switch item is selected or not
	/Accessibility/Default/DirectAccessibility	value to indicate Accessibility settings item is selected or not
	/Accessibility/Default/LongPressTimeout	Setting value of Touch and hold delay (Long press) (500~Integer.MAX)
	/Accessibility/Default/TapDurationEnabled	on/off value of Tap duration (0:off 1:on)
	/Accessibility/Default/TapDurationThreshold	Threshold value of Tap duration (0.1~4.0)
	/Accessibility/Default/TouchBlockingEnabled	on/off value of Ignore repeat (0:off 1:on)
	/Accessibility/Default/TouchBlockingPeriod	Threshold value of Ignore repeat (0.1~4.0)
	/Accessibility/Default/DirectColorLens	directaccess colens assign
	/Accessibility/Default/RemoveAnimations	set remove animations
	/Accessibility/Default/AccessibilityShortcutTargetService	accessibility shortcut target name
	/Accessibility/Default/AccessibilityInteractiveUiTimeoutMs	user interaction time control
	/Accessibility/Default/AccessibilityNonInteractiveUiTimeoutMs	user non-interaction time control

	/Accessibility/Default/MasterBalance	on/off value of Left/Right sound balance (0~100)
	/Accessibility/Default/MasterMono	on/off value of Mono audio (0:off 1:on)
	/Accessibility/Default/StickyKeysEnabled	set sticky key
	/Accessibility/Default/SlowKeysEnabled	set slow key
	/Accessibility/Default/BounceKeysEnabled	set bounce key
	/Accessibility/Default/SlowKeysPeriod	set slow key period
	/Accessibility/Default/BounceKeysPeriod	set bounce key period
	/Accessibility/AssistantMenu/AssistantMenuSize	assistant menu size value (0:small, 1:med, 2:large)
	/Accessibility/AssistantMenu/AssistantMenuActiveItemCount	assistant acitve menu item count
	/Accessibility/AssistantMenu/Transparency	transparency color
	/Accessibility/AssistantMenu/AssistantPlusItemCount	assistant plus item count
	/Accessibility/AssistantMenu/AssistantMenuInactiveItemCount	assistant inactive menu item count
	/Accessibility/AssistantMenu/CursorPointerSpeed	cursor pointer speed
	/Accessibility/AssistantMenu/CursorPointerSize	cursor pointer size
	/Accessibility/AssistantMenu/CursorPadSize	cursor pad size
	/Accessibility/AssistantMenu/AssistantMenuPlusContact	assistant plus on/off
	/Accessibility/AssistantMenu/AssistantMenuPlusCamera	assistant plus on/off
	/Accessibility/AssistantMenu/AssistantMenuPlusEmail	assistant plus on/off
	/Accessibility/AssistantMenu/AssistantMenuPlusGallery	assistant plus on/off
	/Accessibility/AssistantMenu/AssistantMenuPlusDialer	assistant plus on/off
	/Accessibility/AssistantMenu/AssistantMenuPlusMessage	assistant plus on/off
	/Accessibility/AssistantMenu/AssistantMenuPlusBrowser	assistant plus on/off
	/Accessibility/AssistantMenu/AssistantMenuPlusSettings	assistant plus on/off
	/Accessibility/AssistantMenu/AssistantMenuOptionUperapps	assistant option edit
	/Accessibility/AssistantMenu/AssistantMenuOptionLowerapps	assistant option edit
	/Accessibility/AssistantMenu/AssistantMenuShowAsEdgeIcon	set assistant floating icon show/hide
	/Accessibility/UniversalSwitch/Contextual	Show Contextual menu in Action menu (0:off 1:on)
	/Accessibility/UniversalSwitch/EditText	Show Edit text menu in Action menu (0:off 1:on)
	/Accessibility/UniversalSwitch/AutoScan	Move the focus automatically (0:off 1:on)
	/Accessibility/UniversalSwitch/Settings	Icon list in Settings of Action menu
	/Accessibility/UniversalSwitch/SwitchIncreaseVolume	mapping switch with increasing volume
	/Accessibility/UniversalSwitch/MoveApp	Icon list in Move app of Action menu

	/Accessibility/UniversalSwitch/SwitchSelectItem	mapping switch with selecting item
	/Accessibility/UniversalSwitch/AutoMoveWhileHoldingVal	time duration to move focus with next/ previous switch
	/Accessibility/UniversalSwitch/TapDurationVal	time value to tap duration operation
	/Accessibility/UniversalSwitch/Main	Icon list in Main of Action menu
	/Accessibility/UniversalSwitch/Gestures	Icon list in Gestures of Action menu
	/Accessibility/UniversalSwitch/SwitchQuickPanel	mapping switch with open quick panel
	/Accessibility/UniversalSwitch/SoundFeddback	play sound with feedback
	/Accessibility/UniversalSwitch/PauseFirstItemVal	time duration to pause first item
	/Accessibility/UniversalSwitch/AutoMoveWhileHolding	The function to move focus automatically with holding switch
	/Accessibility/UniversalSwitch/PauseFirstItem	Pause the moving focus at the first item
	/Accessibility/UniversalSwitch/CursorColor	value about focusing color
	/Accessibility/UniversalSwitch/SwitchTouchHold	mapping switch with touch and hold
	/Accessibility/UniversalSwitch/IgnoreRepeatVal	time duration to ignore repeat
	/Accessibility/UniversalSwitch/SwitchNotification	mapping switch with open notifications
	/Accessibility/UniversalSwitch/VoiceFeedback	play voice feedback
	/Accessibility/UniversalSwitch/TapDuration	set the function of tap duration
	/Accessibility/UniversalSwitch/SoundFeedbackVol	volume of sound feedback
	/Accessibility/UniversalSwitch/IgnoreRepeat	set the function of ignore repeat
	/Accessibility/UniversalSwitch/SwitchTap	mapping switch with tap operation
	/Accessibility/UniversalSwitch/SelectionMode	state of selection mode at current
	/Accessibility/UniversalSwitch/Buttons	Icon list in Buttons and keys of Action menu
	/Accessibility/UniversalSwitch/SwitchScrollForward	mapping switch with scroll backward
	/Accessibility/UniversalSwitch/AutoTap	set the auto tap
	/Accessibility/UniversalSwitch/SwitchScrollBackward	mapping switch with scroll forward
	/Accessibility/UniversalSwitch/Actions	Icon list in Actions of Action menu
	/Accessibility/UniversalSwitch/RotateScreen	Icon list in Rotate screen of Action menu
	/Accessibility/UniversalSwitch/SwitchRecentApps	mapping switch with showing recent apps
	/Accessibility/UniversalSwitch/SwitchDecreaseVolume	mapping switch with decreasing volume
	/Accessibility/UniversalSwitch/SwitchMoveToNextItem	mapping switch with move next
	/Accessibility/UniversalSwitch/ScanSpeed	value of scan speed
	/Accessibility/UniversalSwitch/AutoTapKeyboard	set the auto tap keyboard
	/Accessibility/UniversalSwitch/EditTextIcon	Icon list in Edit text of Action menu
	/Accessibility/UniversalSwitch/SelectionModeGranularity	state of selection mode granularity at current
	/Accessibility/UniversalSwitch/EditHome	Icon list in Edit home of Action menu
	/Accessibility/UniversalSwitch/LargeCursor	set the width of focus line
	/Accessibility/UniversalSwitch/ScanMethod	set the scan type
	/Accessibility/UniversalSwitch/SwitchHome	mapping switch with move to homescreen

	/Accessibility/UniversalSwitch/SwitchBack	mapping switch with back key
	/Accessibility/UniversalSwitch/GranularitySettings	Icon list in Granularity settings of Action menu
	/Accessibility/UniversalSwitch/SwitchMoveToPreviousItem	mapping switch with move previous
	/Accessibility/UniversalSwitch/ScanLoops	set loop count of auto scan
	/Accessibility/UniversalSwitch/AutoTapVal	time duration for auto tap operation
	/Accessibility/UniversalSwitch/SwitchAutoScan	mapping switch with auto scan on/ off
	/Accessibility/UniversalSwitch/ScanDirection	value of scanning direction
	/Accessibility/UniversalSwitch/SoundFeedback	value of sound feedback
	/Accessibility/VoiceAssistant/PrefKeyboardEcho	Read Keyboard input aloud on/off value(0~2)
	/Accessibility/VoiceAssistant/PrefVibration	Vibration feedback on/off value
	/Accessibility/VoiceAssistant/PrefSpeakRolesKey	Speak element type on/off value
	/Accessibility/VoiceAssistant/PrefQuickMenuLargeCursorKey	Quick menu about Large cursor on/off value
	/Accessibility/VoiceAssistant/PrefWebScripts	Enhance web accessibility on/off value
	/Accessibility/VoiceAssistant/PrefElementIdsKey	Speak Element ID on/off value
	/Accessibility/VoiceAssistant/PrefShortcutUpAndLeft	Gesture action value
	/Accessibility/VoiceAssistant/PrefSelectorActivationKey	Selector activation on/off value
	/Accessibility/VoiceAssistant/PrefShortcutUpAndRight	Gesture action value
	/Accessibility/VoiceAssistant/PrefShortcutLeft	Gesture action value
	/Accessibility/VoiceAssistant/PrefQuickMenuVibraionFeedbakey	Quick menu about vibration feedback on/off value
	/Accessibility/VoiceAssistant/PrefInformationNetwork	Status bar information Signal strangth on/off value
	/Accessibility/VoiceAssistant/PrefPerformanceStatus	Enable performance statics on/off value
	/Accessibility/VoiceAssistant/PrefInformationDate	Status bar information Date on/off value
	/Accessibility/VoiceAssistant/PrefInformationBluetooth	Status bar information Bluetooth on/off value
	/Accessibility/VoiceAssistant/PrefSideTapSensitivity	Gesture action value
	/Accessibility/VoiceAssistant/PrefPitchVolume	Voice pitch volume value
	/Accessibility/VoiceAssistant/PrefTtsOverlay	Show TTS output on/off value
	/Accessibility/VoiceAssistant/PrefSelectorVerbosityKey	Verbosity in Selector setting configuration on/off value
	/Accessibility/VoiceAssistant/PrefA11yHints	Usage hints on/off value
	/Accessibility/VoiceAssistant/PrefShakeToReadThreshold	Shake for continuous reading value
	/Accessibility/VoiceAssistant/PrefSpeakContainerElementPositionsKey	Speak list and grid information on/off value
	/Accessibility/VoiceAssistant/PrefShortcutSideTapDouble	Gesture action value
	/Accessibility/VoiceAssistant/PrefProximity	Mute with proximity sensor on/off value
	/Accessibility/VoiceAssistant/PrefQuickMenuSoundFeedbackkey	Quick menu about sound feedback on/off value

	/Accessibility/VoiceAssistant/PrefDimWhenTalkbackEnabledKey	Dim when talkbck enabled on/off value
	/Accessibility/VoiceAssistant/PrefQuickMenuDarkScreenKey	Quick menu about dark screen on/off value
	/Accessibility/VoiceAssistant/PrefVerbosityPresetKey	Verbosity preset value
	/Accessibility/VoiceAssistant/PrefInformationTime	Status bar information Time on/off value
	/Accessibility/VoiceAssistant/PrefNodeDescOrderKey	Element description order value
	/Accessibility/VoiceAssistant/PrefSelectKeymap	keymap value
	/Accessibility/VoiceAssistant/PrefShortcutRightAndLeft	Gesture action value
	/Accessibility/VoiceAssistant/PrefQuickMenuDeviceVolumeKey	Quick menu about speech volume on/off value
	/Accessibility/VoiceAssistant/PrefSingleTap	Single-tap activation on/off value
	/Accessibility/VoiceAssistant/PrefTreeDebug	Node tree debugging on/off value
	/Accessibility/VoiceAssistant/PrefQuickMenuSpeechRateKey	Quick menu about speech rate on/off value
	/Accessibility/VoiceAssistant/PrefCallerId	Read caller ID aloud on/off value
	/Accessibility/VoiceAssistant/PrefSelectorSpeechRatekey	Speech rate in Selector setting configuration on/off value
	/Accessibility/VoiceAssistant/PrefResumeTalkback	TalkBack resumes from a suspended state. on/off value
	/Accessibility/VoiceAssistant/PrefQuickMenuRapidKeyInputKey	Quick menu about rapid key input on/off value
	/Accessibility/VoiceAssistant/PrefSpeechVolume	Speech volume value(100, 75, 50, 25)
	/Accessibility/VoiceAssistant/PrefShowDimScreenConfirmationDialog	Show dim screen confirmation dialog on/off value
	/Accessibility/VoiceAssistant/PrefSuspended	suspended on/off value
	/Accessibility/VoiceAssistant/PrefInformationBattery	Status bar information Battery power on/off value
	/Accessibility/VoiceAssistant/PrefShortcutDownAndRight	Gesture action value
	/Accessibility/VoiceAssistant/PrefPunctuation	Punctuation on/off
	/Accessibility/VoiceAssistant/PrefUseAudioFocus	Focus on speech audio on/off value
	/Accessibility/VoiceAssistant/PrefSelectorAudioFocusKey	Audio focus in Selector setting configuration on/off value
	/Accessibility/VoiceAssistant/PrefDimVolumeThreeClicks	Setting Value on whether to run Dim Screen with 3 clicks of Volume Key (on/off value)
	/Accessibility/VoiceAssistant/PrefIntonation	Pitch change on/off value
	/Accessibility/ViewClear/MagnifierWindowFollowTypingFocus	change Magnifier typing DB
	/Accessibility/ViewClear/FakeBoldFont	change fake bold font DB
	/Accessibility/VoiceAssistant/PrefShortcutRightAndDown	set shortcut
	/Accessibility/VoiceAssistant/PrefQuickMenuPunctuationKey	Quickmenu for punctuation
	/Accessibility/VoiceAssistant/PrefSoundback	soundback on/off
	/Accessibility/VoiceAssistant/PrefLogLevel	set log level

	/Accessibility/VoiceAssistant/PrefScreenoff	set screen on/off
	/Accessibility/VoiceAssistant/FirstTimeUser	set First time user
	/Accessibility/VoiceAssistant/PrefSoundbackVolume	set soundback volume
	/Accessibility/VoiceAssistant/PrefShowSuspensionConfirmationDialog	set confirmation dialog
	/Accessibility/VoiceAssistant/PrefQuickMenuFocusOnSpeechAudioKey	Quickmenu for focus on speech
	/Accessibility/VoiceAssistant/PrefQuickMenuCursorColorKey	Quickmenu for cursor color
	/Accessibility/VoiceAssistant/PrefQuickMenuNotificationkey	Quickmenu for notification
	/Accessibility/VoiceAssistant/PrefPhoneticLetters	set PhoneticLetters
	/Accessibility/VoiceAssistant/PrefRateVolume	set rate volume
	/Accessibility/VoiceAssistant/PrefSingleTapNavigationBar	set singletap navigation
	/Accessibility/VoiceAssistant/PrefReadScreenKeyboardInputAloud	set read screen keyboard
	/Accessibility/VoiceAssistant/PrefReadHardwareKeyboardInputAloud	set read hardware keyboard
	/Accessibility/VoiceAssistant/PrefInformationCenter	set status bar information
	/Accessibility/VoiceAssistant/PrefSpeakPassword	enable/disable speak passwords
	/Accessibility/VoiceAssistant/PrefEnhancedFocusKey	status enhanced foucus
	/Accessibility/VoiceAssistant/PrefEffectForLightSensingKey	set light sensing effect
	/Accessibility/VoiceAssistant/PrefVoiceForLightSensingKey	set light sensing on/off
	/Accessibility/Default/NotificationReminderType	Notification type
	/Accessibility/Main/HideNotificaiton	Notification hide/show
	/Accessibility/VoiceAssistant/PrefCapitalLettersKey	enable/disable capital letters
	/Accessibility/VoiceAssistant/PrefQuickMenuLightSensingKey	enable light sensing quick menu
	/Accessibility/Default/AssistantMenuEamEnable	set enable assistant plus
	/Accessibility/Default/DirectMuteAllSound	enable direct access mute all sound
	/Accessibility/Default/DirectHighContrastFont	enable direct access hight contrast font
	/Accessibility/Default/AmplifyAmbientSound	enable amplify ambient sound
	/Accessibility/Default/LcdCurtain	enable screen off by side key
	/AirCommand/AirCommand/Shortcuts	The raw string that include the information of shortcut list of the applications that can launch through AirCommand function The version value for the management the setting information of S Pen settings (1~)
	/AirCommand/RemoteSPen/Enabled	The on/off value of S Pen remote function (true/false)
	/AirCommand/RemoteSPen/AppDefinedRule	The raw string that include the various property information about remote action that applications defined

		The version value for the management the setting information of S Pen settings (1~)
	/AirCommand/RemoteSPen/CameraControlRule	The raw string that include the various property information about remote action that RemoteSpen service defined for shutter function The version value for the management the setting information of S Pen settings (1~)
	/AirCommand/RemoteSPen/MediaControlRule	The raw string that include the various property information about remote action that RemoteSpen service defined for media function The version value for the management the setting information of S Pen settings (1~)
	/AirCommand/RemoteSPen/BaseRule	The raw string that include the various property information about remote action that RemoteSpen service defined for the function that quick launch the applications using Spen long click action The version value for the management the setting information of S Pen settings (1~)
	/AirCommand/Spen/ScreenOffMemoEnabled	The on/off value of Screen off memo function (true/false) The value about whether use S Pen signature colour on Screen off memo function or not (true/false)
	/AirCommand/Spen/AirViewEnabled	The on/off value of Air view function (true/false)
	/AirCommand/Spen/WritingBuddyEnabled	The on/off value of Direct pen input function (true/false)
	/AirCommand/Spen/HoveringPointerEnabled	The on/off value of S Pen pointer showing (true/false)
	/AirCommand/AirCommand/FloatingIconEnabled	The on/off value of Floating icon showing (true/false)
	/AirCommand/Spen/SPenDetachmentOption	The integer value that corresponding to an action when S Pen is removed (0:None, 1:Action Memo, 2:Air Command)
	/AirCommand/Spen/SPenAlertEnabled	The on/off value of Alarm function (true/false)
	/AirCommand/Spen/PowerSaverEnabled	The on/off value of Power saver (true/false)
	/AirCommand/Spen/SoundEnabled	The on/off value of Sound (true/false)

	/AirCommand/Spen/VibrationEnabled	The on/off value of Vibration (true/false)
	/AirCommand/RemoteSPen/SPenUnlockEnabled	The on/off value of Unlock with S Pen remote function (true/false)
	/AirCommand/Spen/SPenDoubleTapLaunchEnabled	Press the pen button and press the screen twice with the pen to check whether the note app can be executed (on / off)
	/Routine/Setting/RoutineServiceEnable	Routine enable/disable (true/false)
	/Routine/Preference/HideWidgetLock	Hide widget on Lock screen enable/disable
	/Routine/Preference/ShowRoutineIcon	Show routine icon in home screen enable/disable
	/Routine/Preference/RoutineDeclineMsg	message string value
	/Routine/Preference/IconColorOrder	item background color
	/Routine/Preference/IsPreaddedItem	pre added item
	/Routine/Preference/MainTapIndex	focus item index
	/Routine/Item/RoutineItemList	Routine items information
	/Routine/Common/RoutineBackupVersion	Backup Routine application version
	/SoundAlive/GlobalEffect/Dolby	"Dolby Atmos" setting value for each audio path
	/SoundAlive/GlobalEffect/DolbyOld	"Dolby Atmos" previous setting value for each audio path
	/SoundAlive/GlobalEffect/DolbyUser	"Dolby Atmos" user setting value for each audio path
	/SoundAlive/GlobalEffect/DolbyGameMode	"Dolby Atmos for gaming" setting value for each audio path
	/SoundAlive/Equalizer/PresetIndex	"EQ preset" setting value for each audio path
	/SoundAlive/Equalizer/EQIndex	"EQ index" setting value for each audio path
	/SoundAlive/Equalizer/SquareIndex	"EQ square index" setting value for each audio path
	/SoundAlive/Equalizer/CustomSquareIndex	"EQ custom index" setting value for each audio path
	/SoundAlive/Equalizer/TabIndexCustom	EQ tab index setting value for each audio path
	/SoundAlive/Equalizer/TabCurrentPage	EQ tab page setting value for each audio path
	/SoundAlive/GlobalEffect/UHQUpscaler	"UHQ upscaler" setting value for each audio path
	/SoundAlive/GlobalEffect/UHQUpscalerOld	"UHQ upscaler" previous setting value for each audio path
	/SoundAlive/GlobalEffect/Karaoke	"Karaoke" setting value for each audio path
	/SoundAlive/GlobalEffect/Surround	"Surround" setting value for each audio path
	/SoundAlive/GlobalEffect/TubeAmp	"TubeAmp" setting value for each audio path

	/SoundAlive/GlobalEffect/ConcertHall	"ConcertHall" setting value for each audio path
	/SamsungCloud/Settings/ShowIcon	This value indicates whether there is a cloud app icon on Apps. User can set this value through this step. Settings - Accounts and backup - Samsung Cloud - More - Settings - Show Samsung Cloud icon
	/Finder/Settings/ShowSuggestedApps	Decide whether to show the recommended app when Finder is first launched.
	/Finder/Settings/ShowRecentlyUsedTags	Decide whether to show the tags of recently added.
	/Finder/Settings/ManageApps	Decide apps of getting the searched results.
	/Finder/Settings/ShowSearchSuggestions	Determine of showing recommendations based on search keyword
	/MyFiles/EditMyFilesHome/RecentFiles	Recent files appears on the home screen of My Files (true/false)
	/MyFiles/EditMyFilesHome/Categories	Categories appears on the home screen of My Files (true/false)
	/MyFiles/EditMyFilesHome/SDCard	SD card appears on the home screen of My Files (true/false)
	/MyFiles/EditMyFilesHome/SamsungDrive	Samsung Cloud Drive appears on the home screen of My Files (true/false)
	/MyFiles/EditMyFilesHome/GoogleDrive	Google Drive appears on the home screen of My Files (true/false)
	/MyFiles/EditMyFilesHome/OneDrive	One Drive appears on the home screen of My Files (true/false)
	/MyFiles/FileManagement/Trash	Keep deleted files and folders in the Trash for 30 days before they're deleted forever (true/false)
	/MyFiles/FileManagement/ManageFilesUsingWiFiOnly	Choose whether you can download and edit files in cloud over mobile networks (true/false)
	/MyFiles/FileManagement/ShowHiddenFiles	Show Hidden system files (true/false)
	/MyFiles/StorageAnalysis/LargeFileSize	Select how big files need to be before they're flagged when analyzing storage (25, 100, 500) Select how user custom big files size need to be before they're flagged when analyzing storage (1~1000000MB, 1~976GB) Select how user custom big files size unit need to be before they're flagged when analyzing storage (0: Mega byte, 1: Giga byte)

	/MyFiles/StorageAnalysis/DurationOfUnusedFiles	Select how long files can go unused before they're flagged when analyzing storage (6, 9, 12) Select how user custom long files can go unused before they're flagged when analyzing storage (1~1000 month)
	/MyFiles/EditMyFilesHome/NetworkStorage	Network storage appears on the home screen of My Files (true/false)
	/MyFiles/FileManagement/ManageFilesUsingWiFiOnlyNetworkStorage	Choose whether you can download and edit files in network storage over mobile networks (true/false)
	/MyFiles/FileManagement/ShowFrequentlyUsedOnTop	Display the folders you use most often at the top of Internal storage (true/false)
	/HBD/BackupDeviceInfo	BackupDeviceInfo Class const val API_VERSION = "apiVersion" const val DEVICE_TYPE = "deviceType" const val REGION = "region" const val SALES_CODE = "salesCode" const val ENGINE_TYPE = "engineType" const val HWR_ENGINE_TYPE = "hwrEngineType" const val IS_NOTE_MODEL = "isNoteMode" const val FOLD_DEVICE_TYPE = "foldableDeviceType" const val IS_SPEN_MODEL = "isSpenModel"
	/HBD/Language	Main Input type and sub input type as per languages
	/HBD/CoverLanguage	Main Input type and sub input type as per languages
	/HBD/UsePhonepadInPortrait	Use 3x4 only in portrait view
	/HBD/NumbersAndSymbolsType	Language Dependent / Qwerty Keyboard/ 3x4 Keyboard Language Dependent / Qwerty Keyboard/ 3x4 Keyboard/ 3x4 flick keyboard
	/HBD/CHN/LinkToContacts	LinkToContacts is only used with Chinese devices. If the setting value is on, names and phone numbers from Contract DB can display with Candidate Words and selectable.
	/HBD/UsePredictionOn	Predictive text value ON/OFF
	/HBD/JPN/UseFlickToggleInputKey	Flick toggle input ON/OFF

	/HBD/JPN/UseAutoCursorMovement	Fast / Normal / Slow / Off
	/HBD/UseAutoCapitalize	Auto capitalize ON/OFF
	/HBD/UseAutoPunctuate	Auto punctuate/period ON/OFF
	/HBD/FuzzyPinyinInput	Chinese Fuzzy input selection ON/OFF zh = z, ch = c, sh = s, n = l, h = f, r = l, ang = an, eng = en, ing = in
	/HBD/UseSuggestSticker	Sticker suggestion while typing Bitmoji ON/OFF Mojitok ON/OFF
	/HBD/TextShortcuts	Text Shortcuts data (Shortcuts and phrase
	/HBD/Toolbar/ToolbarSet	main toolbar item main toolbar expose count
	/HBD/Toolbar/ToolbarSubSet	sub toolbar item (winner) sub toolbar expose count(winner)
	/HBD/Toolbar/UseToolbar	Keyboard toolbar ON/OFF
	/HBD/Theme/CustomKeyboardTheme	CustomKeyboardTheme
	/HBD/Theme/KeyboardTheme	Keyboard Theme : Light / Light solid / Dark / Dark solid
	/HBD/Theme/CoverKeyboardTheme	Cover Screen Keyboard theme
	/HBD/Theme/OpenKeyboardTheme	Check if open theme is used or not
	/HBD/HighContrast/UseHighContrast	High contrast keyboard ON/OFF
	/HBD/HighContrast/HighContrastTheme	Hight contrast theme index Yellow / Black1 / Black2 / Blue
	/HBD/ViewType	[OneUI2.1] Standard/One-handed/Floating Standard/Floating/Split Standard/StandardSplit/Floating Bloom view type land [OneUI2.5] Whole phone device can support landscape ViewType. Thus, ViewType values should be seperated for portrait and landscape mode.
	/HBD/KeyboardSize/	KeyboardSize Data Height: 7 levels (3)/ Width: 5 levels (5)
	/HBD/KeyboardTransparency	Transparency min: 77, max: 255
	/HBD/UseNumFirstLine	Number key first line On/OFF
	/HBD/UseCoverNumFirstLine	Cover screen Number key first line
	/HBD/UseAlternativeCharacters	Alternative characters ON/OFF
	/HBD/UseCoverAlternativeCharacters	Cover screen Alternative characters ON/OFF
	/HBD/CustomSymbols	Custom symbol list on cm key
	/HBD/JPN/UsePredictiveTextLines	Predictive text lines (Japanese) 1 / 2 / 3 / 4

	/HBD/KeyboardSwipe	Current Keyboard Swipe (None / Swipe to type / Cursor control)
	/HBD/KeyboardSwipeNone	Keyboard swipe category value none and use swipe
	/HBD/UseSwipeToType	Swipe to type (Continuous Input)
	/HBD/UseCursorControl	Cursor control
	/HBD/TouchAndHoldDelay	Short/ Medium/ Long/ Custom
	/HBD/BackspaceDeleteSpeed	Slow / Normal / Fast
	/HBD/TouchAndHoldSpaceBar	No action / Cursor control / Voice input
	/HBD/KeyTapFeedback/Sound	Keypad Sound feedback ON/OFF
	/HBD/KeyTapFeedback/Vibrate	Keypad vibrate feedback ON/OFF
	/HBD/KeyTapFeedback/Preview	Keypad Character preview while typing ON/OFF
	/HBD/UsePenDetection	Pen detection ON/ OFF
	/HBD/JPN/FlickCustomization	Japanese 8 Flick customization
	/HBD/JPN/UseFlickAngleMultiKey	Narrow / Normal/ Wide
	/HBD/JPN/UseJapaneseInputWordLearning	Use japanese input word learning On / Off
	/HBD/JPN/UseJapaneseWildCardPrediction	Use japanese wild card prediction On / Off
	/HBD/JPN/UseHalfWidthInput	Use half width input On / Off
	/HBD/JPN/UseVoiceInputJapanese	DoCoMo Voice Input / Google Voice Input / None
	/HBD/JPN/UseMushroom	Use / No use
	/HBD/CHN/UseInsertWordWithSpaceKey	Use insert word with space key ON/ OFF
	/HBD/CHN/UseSogouHotWords	Using WLAN only / Use any network / Off
	/HBD/CHN/UseSogouCloudLink	Using WLAN only / Use any network / Off
	/HBD/CHN/UseRareWords	Use rare words ON/ OFF
	/HBD/CHN/UseTraditionalChineseInput	Use traditional Chinese input ON/ OFF
	/HBD/UseSuggestEmoji	Emoji suggestion while typing
	/HBD/UseLanguageSwitchingUsingSpaceBar	Use space bar swipe to change input language
	/HBD/UseLanguageSwitchingUsingKey	Use language switching key to change input language
	/HBD/Hwr/HwrCandidateType	Prediction candidates/ Recognition candidates
	/HBD/Hwr/HwrMode	Multiple characters / Character-by-character / Overlapping characters
	/HBD/Hwr/RecognitionType	Character recognition / Stroke recognition
	/HBD/Hwr/Style	Default / Huizong / Huang Tingjian / Wang Xizhi / Huai Su / Cursive
	/HBD/Hwr/Time	0.1 / 0.3 / 0.5 / 1 / 2 sec
	/HBD/Hwr/Switch	Off / TCH to SCH / SCH to TCH
	/HBD/AutoLmUpdateState	Auto update states

		0 - Never 1 - Using wifi only 2 - whenever available
	/HBD/UsePeriodKeyPopupMultiTap	Period key multi tap setting menu ON/OFF
	/HBD/ViewTypePosition/FloatingMode	Floating keyboard position x,y
	/HBD/ViewTypePosition/SplitMode	Split Floating keyboard position y
	/HBD/KeyboardFontSize	Keyboard View Font Size <Attribute> range (Int) : Font Size Max Range device (Int) : In order to distinguish special devices like Winner, Bloom and normal device(Phone / Tablet)
	/HBD/Moakey	The Moa Key setting menu can be enabled when Korean InputType is Moa Key. The Moa Key setting menu can be enabled when Korean InputType is Moa Key.
	/SamsungCapture/Screenshots/ScreenshotToolbar	Show additional options after you take a screenshot. (on/off)
	/SamsungCapture/Screenshots/DeleteSharedScreenshots	Automatically delete screenshots after they're shared through the screenshot toolbar. (on/off)
	/SamsungCapture/Screenshots/ScreenshotFormat	Screenshot saving format (JPG/PNG)
	/SamsungCapture/ScreenRecorder/Sound	Screen recorder sound setting
	/SamsungCapture/ScreenRecorder/VideoQuality	Screen recorder video quality setting
	/SamsungCapture/ScreenRecorder/SelfieVideoSize	Screen recorder selfie video size setting (Phase 5, 0~4)
	/SamsungCapture/Screenshots/HideStatusAndNavigationBars	Whether status bar and navi bar are included when capturing (on/off)
	/Tag/TagSortingOption	The way how to sort Tag lists
	/Tag/ContentsSortingOption	The way how to sort Searched contents
	/Tag/AddTagIcon	Determination whether Show/Hide tags on launcher
	/DynamicLockScreen/Common/ServiceType	Currently applied wallpaper services type
	/DynamicLockScreen/FreshPack/AppliedPackInfo	Currently applied Dynamic Wallpaper Package Name
ITEM_DATA		
FILE_LIST		